

05/27/2018

This document contains speech commands that apply to Windows Speech Recognition. The left column is an alphabetical listing of actions to be taken on a computer or symbols that may be used. The right column contains the words to be spoken to perform that action or enter that symbol.

This listing uses a set of protocols designed to help you understand what is being displayed. **[Words in brackets in bold print such as this are commands to the computer to do something.]** For example, the "start listening" command that might be included in a script or vocabulary display would show as **[Start listening]**. Words that are not highlighted, such as this, are information for the user. For example, a display such as [say the number shown for the close button] would tell the user to look at the close button and speak the number superimposed on that button.

Dictation is not active in the DOS Command function within Windows; however, from the DOS prompt the Speech Recognition command **[Start Typing]** can be used and characters can be inserted into the DOS window. Some, but not all, speech commands can be used in the DOS window. For example **[Backspace]** has the same effect as in Windows; however, **[undo that]** results in ^Z being displayed.

Dictation works well when using WordPad (**[Open][WordPad]**). Contents of the dictation into WordPad can be selected/highlighted (**[Press] [Control][A as in Alpha]** or **[Select][All]**), copied to the computer's electronic clipboard (**[Press] [Control][C as in Charlie]** or **[Press] [Control][Insert]**), and pasted into another document such as word processing correspondence or an email (**[Press] [Control][V as in Victor]**).

This listing can be searched using a keyboard by pressing and holding down the Control (ctrl) key and pressing the F key, followed by typing the desired word or words in the Find box and pressing the Enter key. Using Speech Recognition, this listing can be searched by saying **[Press] [Control][F as in Foxtrot]** followed by dictating the desired word or words into the Find box and then saying **[Press] [Enter]**. If the desired search result is not displayed, **[Press] [Enter]** can be repeated until the desired result is found or a display indicates it cannot be found. This listing can be open while using Speech Recognition, put out of the way by saying **[Minimize]**, brought back to the screen by saying **[Switch to INTERNET EXPLORER]**, and searched using **[Press] [Control][F as in Foxtrot]**.

Note: Commands may not work in all applications or may work differently in different applications. Many applications have their own keyboard shortcut keys. These can be found by using the Help feature of the application and searching for "keyboard shortcuts" in the Help Index. Say **Press** before saying the desired keyboard shortcut words while using the application.

This document is a work-in-progress compiled from a variety of sources. Send email comments or suggestions for improving this document to wvcomputerclub@gmail.com.

TO DO THIS	SAY THIS (Note: some commands are context-based)
Activate Menu Bar options (underlined letters)	[Press] [F10]
Add a new word to the speech dictionary	[Open][Speech Dictionary]
Add hyphens to a selected word or phrase	[Add][hyphens to that]
Add to Favorites	[Press] [Control][D as in Delta]
Add, delete or edit words in your Speech Dictionary	[Open Speech Dictionary]
Backspace or delete the character to the left of the cursor	[Backspace]
Bold selected text	[Press] [Control][B as in Bravo] or [Bold]
Capitalize all letters of each word in a phrase or sentence	[All Caps] [words to be capitalized] or [Select] [first word] [to] [last word], then [All Caps][that]
Capitalize all the letters of the word	[All caps] [word]
Capitalize first letter of each word in a phrase or sentence	[Capitalize] [words to be capitalized] or [Select] [first word] [to] [last word], then [Capitalize][that]
Capitalize following letters	[Press] [Caps Lock]
Capitalize the first letter of the word	[Capitalize] [word]

Center text	[Press] [Control][E as in Echo]
Change case (upper/lower) in selected text (Microsoft Word)	[Change case] [say selection choice]
Change existing words in Speech Dictionary	[Open][Speech Dictionary]
Change the next number of words to lowercase	[Change][next] [number of] [words] [to lowercase]
Change the next number of words to uppercase	[Change][next] [number of] [words] [to uppercase]
Clear the selection on the screen	[Clear][selection];[unselect][that]
Click a numbered item	[number] [OK]
Click an item by saying its name	[File]; [Edit]; [View]; [Save]; [Bold];[Start]
Click any item	[Click][File]; [Click][Bold]; [Click][Save]; [Click][Close]
Click any mousegrid square	[Click][number of the square]
Click item	[Click][Recycle Bin] or [Click][Computer] or [Click][File]
Click something you don't know the name of	[Show Numbers] (Numbers will appear on the screen for every item in the active window)
Close a program	[Close that]; [Close][Paint]; [Close][Documents]; [Close][Internet Explorer]; [Press] [Alt][F4] (only works with the active window)
Close active document in program that allows multiple open documents	[Press] [Control][F4]
Close current application or pop-up/window	[Press] [Alt][F4]
Close the current window or application. If none, starts Shut Down	[Press] [Alt][F4]
Collapse selected item in a table of contents or directory tree	[Press] [Left Arrow]
Copy	[Copy][that]; [Copy]
Copy active window image to computer's electronic clipboard	[Press] [Alt][Print Screen]
Copy highlighted (selected) text or image to computer's electronic clipboard	[Press] [Control][C as in Charlie]; [Copy][that]; [Copy]
Copy screen display to computer's electronic clipboard	[Press] [Print Screen]
Copy selected text to clipboard	[Press] [Control][C as in Charlie] or [Press] [Control][Insert] or [Copy]
Create a new folder	[Press] [Control][Shift][N as in November]
Cut selected text or image	[Cut][that];[Cut];[Press] [Control][X as in Xray]
Cycle through items in the order they were opened	[Press] [Alt][Escape]
Cycle through programs on Taskbar using 3D Aero Flip	[Press] [Control][Windows][Tab]
Cycle through programs on task bar	[Press] [Alt][Escape]
Cycle through programs using 3D Aero Flip	[Press] [Windows][Tab]
Cycle through programs using arrow keys and Enter to open application	[Press] [Alt][Control][Tab]; then [Up Arrow] or [Down Arrow] repeatedly until desired application is highlighted; then [Enter]
Delete	[Delete][that]; [Delete];[Strike][that];[Undo][that]
Delete an item without placing it in the Recycle Bin	[Press] [Shift][Delete]
Delete selected text and write it to the clipboard	[Press] [Control][X as in Xray] or [Press] [Shift][Delete]
Delete the character at the cursor	[Delete]
Delete the next paragraph	[Delete][next][paragraph]
Delete the next sentence	[Delete][next][sentence]
Delete the previous paragraph	[Delete][previous][paragraph]
Delete the previous sentence	[Delete][previous][sentence]
Delete the selected or last dictated text	[Delete][that]
Delete to the end of the current document	[Delete][to end of][document]
Delete to the end of the current paragraph	[Delete][to end of][paragraph]
Delete to the end of the current sentence	[Delete][to end of][sentence]
Delete to the end of the current word	[Delete][to end of][word]
Delete to the start of the current document	[Delete][to start of][document]
Delete to the start of the current paragraph	[Delete][to start of][paragraph]
Delete to the start of the current sentence	[Delete][to start of][sentence]
Delete to the start of the current word	[Delete][to start of][word]

Display Favorites in Internet Explorer	[Press] [Alt][C as in Charlie]
Display Help home page	[Press] [Alt][Home]
Display available commands	[Show speech options]
Display or hide previous pane	[Press] [Alt][P as in Papa]
Display or hide the Start menu	[Press] [Windows]
Display support page	[Press] [Alt][A as in Alpha]
Display the Address bar list in My Computer, Edge, Windows Explorer or Internet Explorer	[Press] [F4]
Display the items in an active list	[Press] [F4]
Display the next higher level in a system tree display	[Press] [Backspace]
Display the shortcut menu for the selected (highlighted) item	[Press] [Shift][F10] or [Show Context Menu]
Do not insert a space before the next word	[No space]
Double Underline selected text (Microsoft Word)	[Press] [Control][Shift] [D as in Delta]
Double-click a numbered item	[Double-click][number]
Double-click an item	[Double-click][Computer]; [Double-click][Recycle Bin]; [Double-click][Folder name];[Double-click][File name]
Enable dictation everywhere	[Enable dictation everywhere];[Show speech options] [options] [dictation everywhere]
Exit Magnifier	[Press] [Windows][Escape]
Expand selected item in a table of contents or directory tree	[Press] [Right Arrow]
Extend selected (highlighted) area to the next line	[Press] [Shift][Down Arrow] or add [number of times] [times]
Extend selected (highlighted) area to the previous line for multiples	[Press] [Shift][Up Arrow] or add [number of times] [times] for multiples
Find and replace word or words	[Press] [Control] [H as in Hotel]
Find text	[Press] [Control][F as in Foxtrot]
Go down one line	[Press] [Down Arrow] or add [number of times][times] for multiples
Go left one character	[Press] [Left Arrow] or add [number of times][times] for multiples
Go left one word	[Press] [Control][Left Arrow] or add [number of times][times] for multiples
Go right one character	[Press] [Right Arrow] or add [number of times][times] for multiples
Go right one word	[Press] [Control][Right Arrow] or add [number of times] [times] for multiples
Go to	[Press] [Control][G as in Golf]
Go to a field in a form or a program such as cc in email	[Go to][field name]; [Go to][Subject]; [Go to][Address]
Go to beginning of current line, text box or list	[Press] [Home]
Go to beginning of current paragraph or cell, or if not in a paragraph or cell, to the end of the previous paragraph or cell	[Press] [Control][Up Arrow]
Go to end of current line, text box or list	[Press] [End]
Go to end of current paragraph or cell, or if not in a paragraph or cell, to the beginning of the next paragraph or cell	[Press] [Control][Down Arrow]
Go to first item in System Tray	[Press] [Windows][B as in Bravo]
Go to first item on Taskbar	[Press] [Windows][T as in Tango]
Go to the end of the current document	[Go to][end of][document] or [Press] [Control][End]
Go to the end of the paragraph the cursor is in	[Go to][end of][paragraph]
Go to the end of the sentence that the cursor is in	[Go to][end of][sentence]
Go to the start of the document	[Go to][start of][document] or [Press] [Control] [Home]
Go to the start of the paragraph the cursor is in	[Go to][start of][paragraph]
Go to the start of the sentence that the cursor is in	[Go to][start of][sentence]
Go up one line	[Press] [Up Arrow] or add [number of times][times] for multiples

Highlight contents of Address box in Windows Explorer or Internet Explorer (use to copy addresses)	[Press] [F6]
Insert a line break	[Press] [Shift][Enter]
Insert a new line in the document	[New line] or add [number of times][times] for multiples
Insert a new paragraph in the document	[New paragraph]
Insert a nonbreaking hyphen	[Press] [Control][Shift][Hyphen]
Insert a page break	[Press] [Control][Enter]
Insert a tab	[Insert Tab]
Insert current date (Microsoft Word)	[Press] [Alt][Shift][D as in Delta]
Insert the literal word for the next command; for example you can insert the word "comma" instead of the punctuation mark	[Literal] [word]
Insert the numeral form of a number	[Numeral] [number]
Invert colors in Magnifier display	[Press] [Control][Alt] [I as in India]
Italicize selected text	[Press] [Control][I as in India]
Justify text	[Press] [Control] [J as in Juliet]
Left-align text	[Press] [Control] [L as in Lima]
Left-click on current cursor location	[Press] [Enter]
Lower case all letters of each word in a phrase or sentence	[No caps] [words to be capitalized] or [Select] [first word][to][last word], then [No caps][that]
Make all the letters in the word lowercase	[No caps] [word]
Make the computer listen to you	[Start listening]
Make the computer stop listening	[Stop listening]
Maximize	[Maximize][that]; [Maximize][Paint]; [Maximize] [Internet Explorer] (only works with the active window)
Maximize window	[Press] [Alt][Space][X as in Xray]
Maximize window if Restored	[Press] [Windows][Up Arrow]
Minimize	[Minimize][that]; [Minimize][Paint]; [Minimize][Internet Explorer] (only works with the active window)
Minimize all open windows and display desktop	[Press] [Windows][D as in Delta] or [Minimize][All] [Windows]
Minimize all taskbar items and displays desktop	[Press] [Windows][M]
Minimize all windows	[Press] [Windows][M as in Mike]; [Minimize all] [Windows]
Minimize all windows; return to previous state	[Press] [Windows][D as in Delta]
Minimize the microphone bar	[Minimize][speech recognition] To reset, say [Maximize] [speech recognition]
Minimize window	[Press] [Alt][Space][N as in November]
Move Restored window to left	[Press] [Windows][Left Arrow]
Move Restored window to right	[Press] [Windows][Right Arrow]
Move active window to left side of screen	[Press] [Windows][Left Arrow]
Move active window to right side of screen	[Press] [Windows][Right Arrow]
Move back to previous pane, box or cell	[Press] [Left Arrow]
Move backward through options in a dialogue box	[Press] [Shift][Tab]
Move backward through tabs	[Press] [Control][Shift][Tab]
Move forward to next pane, box or cell	[Press] [Right Arrow]
Move insertion point to beginning of next word	[Press] [Control][Right Arrow]
Move insertion point to beginning of previous word	[Press] [Control][Left Arrow]
Move one window to the left	[Press] [Control][Page Up]
Move one window to the right	[Press] [Control][Page Down]
Move screen down one line	[Press] [Control][Down Arrow]
Move screen one page down	[Press] [Page Down]
Move screen one page up	[Press] [Page Up]
Move screen up one line	[Press] [Control][Up Arrow]
Move the Speech Recognition microphone icon out of the way	[Move][speech recognition]

Move the mouse pointer to the center of any mousegrid square	[number of the square] or [numbers of the square]; 1; 7; 9; 1, 7, 9
Open Command Prompt (DOS Prompt)	[Open][Command]
Open Computer	[Open][Computer] or [Press] [Control] [Windows][F as in Foxtrot]
Open Control Panel	[Open][Control Panel]
Open Ease of Access Center	[Ease of Access]
Open Find Files dialogue box; Save As	[Press] [F3]
Open Find dialog window	[Press] [Control][F as in Foxtrot]
Open Mobility Center	[Press] [Windows][X as in Xray]
Open My Computer	[Press] [Windows][E as in Echo]
Open Print box	[Press] [Control][P as in Papa]
Open Run Dialog box	[Open][Run] or [Press] [Windows][R as in Romeo]
Open Snipping Tool	[Open][Snipping Tool]
Open System Properties box	[Press] [Windows][Break]
Open Task Manager and cycle through programs in reverse direction	[Press] [Alt][Shift][Tab]
Open Utility Manager (for Ease of Access)	[Press] [Windows][U as in Uniform]
Open Windows Help	[Press] [Windows][F1]
Open a file or application in Internet Explorer	[Press] [Control][O as in Oscar]
Open a new tab in Internet Explorer	[Press] [Control][T as in Tango]
Open a new window in Internet Explorer	[Press] [Control][N as in November]
Open a program	[Open][Paint]; [Open][WordPad]; [Open][program name]
Open application help menu or Windows help menu if not in an application	[Press] [F1]
Open print preview in word processor	[Press] [Control][F2]
Open programs/files on taskbar	[Press] [Windows][sequence number]
Open the Control Menu for a document	[Press] [Alt][Hyphen]
Open the DOS prompt	[Open][Command]. Say [Close] [Command] to close.
Open the Start Menu	[Press][Control][Escape] or [Start] or [Press][Windows Key]
Paste	[Paste]
Paste contents of electronic clipboard into active window location	[Press] [Control][V as in Victor] or [Press] [Shift][Insert] or [Paste]
Perform the action for the highlighted or selected item	[Press] [Enter]
Press any key on the keyboard	[Press] [keyboard key]; [Press] [a]; [Press] [capital b]; [Press] [Shift] [a]; [Press] [Control][a]
Press certain keyboard keys without saying "Press" first	[Delete]; [Backspace]; [Enter]; [Page Up]; [Page Down]; [Home]; [End]; [Tab] or add [number of times][times] for multiples
Press toolbox word with an underlined letter	[Press][Alt][the underlined letter] For example, if you want to click on Tools, you would say [Press] [Alt][T as in Tango]
Prevent a CD from automatically playing	[Press] [Shift] when inserting a CD into the CD-ROM drive
Prevent a word from being dictated	[Open][Speech Dictionary]
Print	[Press] [Control][P as in Papa]
Print selected text	[Select][first word][to][last word], then [Press] [Control][P as in Papa], then [Show Numbers], then [number for Selected Text circle][OK][Print]
Projector selection options	[Press] [Windows][P as in Papa]
Put icon on desktop	[Mousegrid] repeat numbers to put grid on an open area of the document; [Right-click][Create Shortcut][Yes]
Put the cursor after a specific word	[Go after] [word]

Put the cursor before a specific word	[Go to] [word]
Redo an Undo	[Press] [Control][Shift][Z as in Zulu]
Refresh the current window	[Press] [F5]
Remove hyphens from a selected word or phrase	[Remove][hyphens to that]
Rename a selected item	[Press] [F2]
Restore	[Restore][that]; [Restore][Paint]; [Restore][Internet Explorer] (only works with the active window) This command shifts from full screen display to a screen.
Restore window	[Restore][Window] or [Press] [Alt][Space][Enter]
Right-align text	[Press] [Control][R as in Romeo]
Right-click a numbered item	[Right-click][number]
Right-click any item	[Right-click][Computer]; [Right-click][Recycle Bin];[Right- click] [Folder name];[Right-click][file name]
Rotate screen display in direction of arrow	[Press] [Control][Alt][Arrow Key]
Save current document	[Press] [Control][S as in Sierra]
Scroll an exact distance in other units	[Scroll][up][number]; [Scroll][down][number]
Scroll an exact distance in pages	[Scroll][down][number][pages]; [Scroll][up][number][pages]
Scroll direction	[Scroll][up]; [Scroll][down]; [Scroll][left];[Scroll][right]
Scroll down a list, one screen at a time	[Press] [Page Down]
Scroll up a list, one screen at a time	[Press] [Page Up]
Select All	[Press] [Control][A as in Alpha];[Select][All]
Select a file name in a directory listing	[name of file]
Select a word and start to correct it	[Correct][word]
Select a word in a document	[Select][word]
Select an area where you want to drag the item with the mousegrid (Can also be used to resize windows)	[number--or numbers--of the square where you want to drag]; 4, 5, 6 (followed by) [Click]
Select an item to drag with the mousegrid (Can also be used to resize windows)	[number--or numbers--of the square where the item appears]; 3, 7, 9 (followed by) [Mark]
Select and delete specific words	[Delete][words]
Select character to left of cursor	[Press] [Shift][Left Arrow]
Select character to right of cursor	[Press] [Shift][Right Arrow]
Select everything in a document	[Select][All] or [Press] [Control][A as in Alpha]
Select full window of lines downward	[Press] [Shift][Page Down]
Select full window of lines upward	[Press] [Shift][Page Up]
Select last number of characters	[Select][last][1-20][characters]
Select last number of letters	[Select][last][1-20][letters]
Select last number of sentences	[Select][last][1-20][sentences]
Select last number of words	[Select][last][1-20][words]
Select line above line on which cursor is located	[Press] [Shift][Up Arrow]
Select line on which cursor is located	[Press] [Shift][Down Arrow]
Select multiple contiguous documents in a system tree display	[Press] [Shift][Up Arrow] or [Press] [Shift][Down Arrow]
Select next number of characters	[Select][next][1-20][characters]
Select next number of letters	[Select][next][1-20][letters]
Select next number of sentences	[Select][next][1-20][sentences]
Select next number of words	[Select][next][1-20][words]
Select next word	[Press] [Control][Shift][Right Arrow] or add [number of times][times] for multiples
Select or cancel selection of character to the left	[Press] [Shift][Left Arrow] or add [number of times][times] for multiples
Select or cancel selection of character to the right	[Press] [Shift][Right Arrow] or add [number of times][times] for multiples
Select or cancel selection of one line of text down	[Press] [Shift][Down Arrow] or add [number of times][times] for multiples

Select or cancel selection of one line of text up	[Press] [Shift][Up Arrow] or add [number of times][times] for multiples
Select or cancel selection of one screen of text down for multiples	[Press] [Shift][Page Down] or add [number of times][times]
Select or cancel selection of one screen of text up	[Press] [Shift][Page Up] or add [number of times][times] for multiples
Select or clear the check box if the active option is a check box	[Press] [Space]
Select previous number of characters	[Select][previous][1-20][characters]
Select previous number of letters	[Select][previous][1-20][letters]
Select previous number of sentences	[Select][previous][1-20][sentences]
Select previous number of words	[Select][previous][1-20][words]
Select previous word	[Press] [Control][Shift][Left Arrow] or add [number of times][times] for multiples
Select text to beginning of line	[Press] [Shift][Home] or add [number of times][times] for multiples
Select text to start of document	[Press] [Control][Shift][Home]
Select the 1-20 words after the location of the cursor	[Select][next][1-20][words]
Select the 1-20 words before the location of the cursor	[Select][previous][1-20][words]
Select the word in the current document	[Select][word]
Select to end of document	[Select][to end of][document]
Select to end of paragraph	[Select][to end of][paragraph]
Select to end of sentence	[Select][to end of][sentence]
Select to end of word	[Select][to end of][word]
Select to start of document	[Select][to start of][document]
Select to start of paragraph	[Select][to start of][paragraph]
Select to start of sentence	[Select][to start of][sentence]
Select to start of word	[Select][to start of][word]
Select/highlight to beginning of current paragraph	[Press] [Control][Shift][Up Arrow]
Select/highlight to end of current paragraph	[Press] [Control][Shift][Down Arrow]
Set window to Restored if Maximized; Minimized if Restored	[Press] [Windows][Down Arrow]
Show Desktop	[Show Desktop]
Show Menu applicable to current context	[Show Context Menu]
Show Start Menu	[Show Start Menu]
Show a list of applicable commands	[What can I say?]
Show menu applicable to right-clicking current display	[Show right click menu]
Show system properties	[Open][system properties] or [Show][system properties]
Show the mousegrid	[Mousegrid]
Shut down computer	[Mousegrid][7][7][7][OK][Show Numbers][28][OK][shut down][OK]
Single space lines	[Press] [Shift][Enter]
Start a new page	[Press] [Control][Enter]
Start new instance of application in n (1 through ?) position in Taskbar	[Press] [Shift][Windows][n]
Start slide show in PowerPoint; refresh Windows Explorer display	[Press] [F5]
Start typing multiple keyboard characters without needing to say "Press" before each character	[Start typing] or [Start pressing keys]
Stop execution of current action	[Press] [Escape]
Stop typing multiple keyboard characters without needing to say "Press" before each character	[Stop typing] or [Stop pressing keys]
Switch to an open program	[Switch to][Paint];[Switch to][WordPad];[Switch to] [program name];[Switch][application];[Press][Alt] [Escape]
Switch to last-used application or window	[Press] [Alt][Tab] If necessary, repeat until the desired application becomes the current application

Switch to or open application in n(1 through ?) position in Taskbar	[Press] [Windows][n]
To copy monitor screen to the clipboard	[Press] [Print Screen] If unsuccessful, say [Press] [Alt][Print Screen] or [Press] [Shift][Print Screen]
To get help with current application	[Press] [F1] or [Press] [Alt][H as in Hotel] or [Help]
Toggle between character insert mode and character replace mode	[Press] [Insert]
Turn Caps Lock on/off	[Press] [Caps Lock]
Turn Number Lock\Num Lock On or Off	[Press] [Number Lock] or [Press] [Num Lock]
Turn bold on or off, or bold selected text	[Press] [Control][B as in Bravo]
Turn italics on or off, or italicize selected text	[Press] [Control][I as in India]
Turn underline on or off, or underline selected text	[Press] [Control][U as in Uniform]
Undo	[Undo][that] or [Scratch][that] or [Undo] or [Press] [Control][z as in Zulu] or [Press] [Alt][Backspace]
Undo last action	[Press] [Control][Z as in Zulu]
Unselect a file in a directory listing	[Press] [Control][Spacebar]
Update the list of currently available speech commands	[Refresh speech commands]
View properties for selected item	[Press] [Alt][Enter]
Windows Flip 3D function	[Press] [Windows][Tab]
Zoom out in Magnifier	[Press] [Windows][Minus]

SYMBOLS

TO DISPLAY THIS	SAY THIS
&	[Ampersand]; [and sign]
'	[Apostrophe]
*	[Asterisk]
@	[At sign]
`	[Back quote]
\	[Backslash]
^	[Caret]
¢	[Cent sign]
>	[Close angle bracket]
"	[Close angle quote]
}	[Close brace]; [Close curly bracket]
]	[Close bracket]; [Close square bracket]; [Right square bracket]
"	[Close double quote]; [Close quote]
)	[Close parenthesis]; [Close paren]
'	[Close single quote]
:	[Colon]
,	[Comma]
©	[Copyright sign]
°	[Degree sign]
÷	[Division sign]
//	[Double slash]
...	[Ellipsis]; [Dot dot dot]
-	[Em dash]; [Double dash]
-	[En dash]
=	[Equal sign]
!	[Exclamation mark]; [Exclamation point]
/	[Forward slash]
:-)	[Frowny face]
f	[Function sign]
>	[Greater than sign]

-	[Hyphen]; [Minus sign]; [Dash]
<	[Less than sign]
x	[Multiplication sign]
¬	[Not sign]
#	[Number sign]; [Pound sign]; [Press][Hash sign]
1/2	[One half sign]
1/4	[One quarter sign]
<	[Open angle bracket]
"	[Open angle quote]
{	[Open brace]; [Open curly bracket]
[[Open bracket]; [Open square bracket]; [Left square bracket]
"	[Open double quote]; [Open quote]
([Open parenthesis]; [Open paren]
'	[Open single quote]
¶	[Paragraph sign]
%	[Percent sign]
.	[Period]; [Dot]; [Press][Decimal point]
±	[Plus or minus sign]
+	[Plus sign]
£	[Pound sterling sign]
¤	[Press][General currency sign]
¨	[Press][Umlaut]
?	[Question mark]
®	[Registered sign]; [Registered trademark sign]
§	[Section sign]
;	[Semicolon]
:)	[Smiley face]
3/4	[Three quarter sign]; [Three-fourths]
~	[Tilde]
™	[Trademark sign]
_	[Underscore]
	[Vertical bar]
;-)	[Winky face]
¥	[Yen sign]